



[Dec-2016-New010-151 VCE Dumps Free 85Q&As Offered for Downloading in Braindump2go[NQ21-NQ30]


2016/12 New Cisco 010-151: Supporting Cisco Data Center System Devices Exam Questions Updated Today! Free Instant Download 010-151 Exam Dumps (PDF & VCE) 85q from Braindump2go.com Today! 100% Real Exam Questions! 100% Exam Pass Giaranteed! 1. | 2016/12 New 010-151 Exam Dumps (PDF & VCE) 85q Download: <http://www.braindump2go.com/010-151.html> 2. | 2016/12 New 010-151 Exam Questions & Answers: <https://1drv.ms/f/s!AvI7wzKf6QBjgUA0ldnAmKoPR142> QUESTION 21 Which command saves the active configuration to NVRAM? A. copy startup-config running-config B. copy active-config backup-config C. copy running-config startup-config D. copy backup-config active-config Answer: C QUESTION 22 Refer to the exhibit.




Where is the best place to see bootflash free space? A. A - Available Memory B. B - Total Memory C. C - Local Storage Information D. D - High Availability Details Answer: C QUESTION 23 Refer to the exhibit.



Where is the best place to find the B200 BIOS version used in a specific Cisco UCS Manager version? A. A - Installed Firmware B. B - Packages C. C - Images D. D - Capability Catalog E. E - Management Extension Answer: B QUESTION 24 Refer to the exhibit.



Which option should you select to get the output of the show tech-support detail command for the Cisco UCS B-Series blade? A. A - ucsm B. B - chassis C. C - fabric-extender D. D - rack-server Answer: B QUESTION 25 Which command syntax is correct to reset the admin password when the switch is in the kickstart prompt "switch(boot) #"? A. exec -> admin-password <password> B. connect local-mgmt -> admin-password <password> C. configure terminal -> admin-password <password> D. connect nxos -> admin-password <password> E. admin-password <password> Answer: C QUESTION 26 Refer to the exhibit.



Where is the best place to see the power supply status of the blade server enclosure? A. A - Chassis 1B. B - Chassis 1 - PSUsC. C - Chassis1 - ServersD. D - Rack-Mounts - ServersE. E - Fabric Interconnects A - PSUs Answer: B QUESTION 27To do a password recovery on a Cisco NX-OS Switch, which option shows the correct syntax to display the bootflash contents at the switch(boot)#? A. display bootflash:B. show bootflash:C. dir bootflash:D. find bootflash: Answer: C QUESTION 28Which Cisco NX-OS command displays kernel uptime? A. show moduleB. show versionC. show licenseD. show bootE. show interface Answer: B QUESTION 29Which two commands display the version of Cisco NX-OS code that the device is currently running on? (Choose two.) A. show versionB. show moduleC. show interfaceD. show bootE. show license Answer: AB QUESTION 30On the Sensors page from the CIMC view, which four tabs are displayed to view further information? (Choose four.) A. Power SupplyB. FanC. MemoryD. CPUE. LEDSF. Temperature Answer: ABEF !!!RECOMMEND!!!
1.Braindump2go|2016/12 New 010-151 Exam Dumps (PDF & VCE) 85q Download:<http://www.braindump2go.com/010-151.html>
2.Braindmp2go|2016/12 New 010-151 Exam Questions & Answers: YouTube Video: [YouTube.com/watch?v=Q9lmi-oPi1I](https://www.youtube.com/watch?v=Q9lmi-oPi1I)