

[May-2019-New100% Exam Pass-300-075 PDF Dumps Free from Braindump2go

[2019/May Braindump2go Cisco CCNP Collaboration CIPTV2 300-075 Dumps with PDF and VCE New Updated Today!](#)

Following are some new 300-075 Exam Questions:1.|2019 Latest 300-075 Exam Dumps (PDF & VCE) Instant

Download:<https://www.braindump2go.com/300-075.html>2.|2019 Latest 300-075 Exam Questions & Answers Instant

Download:<https://drive.google.com/drive/folders/0B75b5xYLjSSNOXRpM1hydUpDU3M?usp=sharing>New QuestionIf you want to

delete a SAF-enabled trunk from Cisco Unified Communications Manager Administration, what must you do first?A. Disassociate the trunk from the CCD advertising service or CCD requesting service.B. Delete the trunk from the CCD requesting service node.

C. Place the Cisco Unified Communications Manager node in standby mode.D. Redirect CCD advertising and requesting

services to another Cisco Unified Communications Manager.**Answer: A**New QuestionWhich functionality does ILS use to link all hub clusters in an ILS network?A. FullmeshB. AutomeshC. ILS updatesD. multicast**Answer: B**New QuestionWhich optiona

is known as the location attribute that the global dialplan replication uses to advertise its dial plan information?A. location

controllerB. route patternC. route stringD. URI**Answer: C**New QuestionRefer to the exhibit. If an IP phone in San Jose roams

to New York, which two IP phone settings will be modified by Device Mobility so that the phone can place and receive calls in New York? (Choose two.) A. The physical locations are not different, so the configuration of the phone is not modified.B. The

physical locations are different, so the roaming-sensitive parameters of the roaming device pool are applied.C. The device mobility

groups are the same, so the Device Mobility-related settings are applied in addition to the roaming-sensitive parameters.D. The

Device Mobility information is associated with one or more device pools other than the home device pool of the phone, so one of the

associated device pools is chosen based on a round-robin load-sharing algorithm.E. The Device Mobility information is associated

with the home device pool of the phone, so the phone is considered to be in its home location. Device Mobility will reconfigure the

roaming- sensitive settings of the phone.**Answer: BC**New QuestionWhat happens when a user logs in using the Cisco Extension

Mobility Service on a device for which the user has no user device profile?A. The Extension Mobility log in fails.B. The device

takes on the default device profile for its type.C. The user can log in but does not have access to any features, soft key templates,

or button templates.D. The device uses the first device profile assigned to the user in Cisco Unified Communications Manager.

Answer: BNew QuestionWhich three steps are required when configuring extension mobility in Cisco Unified Communications

Manager? (Choose three.)A. Create the extension mobility IP Phone Service.B. Check the Home Cluster checkbox on the End

User Configuration page.C. Check the Enable Extension Mobility checkbox on the Directory Number Configuration page.D.

Unsubscribe all other services from the Cisco IP Phone.E. Create a user Device Profile.F. Subscribe the extension mobility IP

Phone Service to the user Device Profile.**Answer: AEF**New QuestionHow many Cisco Unified Mobility destinations can be

configured per user?A. 1B. 10C. 4D. 6**Answer: B**New QuestionWhen configuring Cisco Unified Mobility, which parameter

defines the access control for a call that reaches out to a remote destination?A. Calling Party Transformation Calling Search Space

under Remote Destination Profile InformationB. User Local under Remote Destination Profile InformationC. Rerouting Calling

Search Space under Remote Destination Profile InformationD. Rerouting Calling Search Space under Remote Destination

informationE. Calling Search Space under Phone Configuration**Answer: C**New QuestionWhich two bandwidth management

parameters are available during the configuration of Cisco Unified Communications Manager regions? (Choose two.)A. Default

Audio Call RateB. Max Audio Bit RateC. Default Video Call RateD. Max Video Call Bit Rate (Includes Audio)E. Max

Number of Video Sessions**Answer: BD**New QuestionIn Cisco Unified Communications Manager, where do you configure the

default bit rate for audio and video devices?A. Enterprise ParametersB. Region under Region InformationC. Cisco

CallManager service under Service Parameter ConfigurationD. Enterprise Phone Configuration**Answer: C**Explanation:For

enhanced scalability and to conserve resources, Cisco recommends that you properly set the default values in the Clusterwide

Parameters (System - Location and Region) section of the Cisco Unified Communications Manager AdministrationService

Parameters Configuration window for the audio codec, video call bandwidth, and link loss type values and then choose the Use

System Default entries in the Cisco Unified Communications Manager Administration Region Configuration window for these

fields.

https://www.cisco.com/c/en/us/td/docs/voice_ip_comm/cucm/admin/9_1_1/ccmcfg/CUCM_BK_A34970C5_00_admin-guide-91/CUCM_BK_A34970C5_00_admin-guide-91_chapter_0111.htmlNew QuestionWhich module is the minimum PVDMM3 module

needed to support video transcoding?A. PVDMM3-32B. PVDMM3-64C. PVDMM3-128D. PVDMM3-192**Answer: C**

!!!RECOMMEND!!!1.|2019 Latest 300-075 Exam Dumps (PDF & VCE) Instant

Download:<https://www.braindump2go.com/300-075.html>2.|2019 Latest 300-075 Study Guide Video Instant Download: YouTube

Video: [YouTube.com/watch?v=S2wMYKmsGoc](https://www.youtube.com/watch?v=S2wMYKmsGoc)